

Protocol for generation of Lentivirus from 293T cell

Introduction:

Based on our innovative polymer synthesis technology, PeneFect™ Plus DNA In Vitro Transfection Reagent is formulated to be a powerful transfection Reagent that ensures effective and reproducible transfection with less cytotoxicity. PeneFect™ reagent was shown to deliver DNA to various established cell lines as well as primary cells. PeneFect™ reagent was shown to generate lentivirus with extremely high titers from 293T cells.

Important Guidelines for Transfection:

- For high titer of lentivirus, 293T cell must be healthy. Please grow the 293T cell per supplier's instruction.
- For high efficiency, transfect cells at high density. ~90% confluency is highly recommended.
- To lower cytotoxicity, transfect cells in presence of serum (10%) and antibiotics.
- Use serum-free DMEM with High Glucose to dilute PeneFect™ reagent and DNA. The diluent must be serum-free.

Procedures for Transfecting 293T Cells

Cell Seeding:

Cells should be plated 18 to 24 hrs prior to transfection so that the monolayer cell density reaches to the optimal ~90% confluency at the time of transfection. Complete culture medium with serum and antibiotics is freshly added to each well 30~60 min before transfection.

Note: High serum levels (>5%) with antibiotics usually do not have inhibitory effect on transfection efficiency. For some specific 293 cells, maximal transfection efficiencies are observed in the presence of serum and antibiotics. We recommend using complete serum/antibiotics-containing medium initially.

Preparation of PeneFect™/DNA Complex and Transfection Procedures:

The following protocol is given for transfection in 10 cm dish. For other culture formats, scale up or down per culture dish's surface. The optimal transfection conditions are given in the standard protocol described below.

- Cell confluency should be ~90 % at the day of transfection
- For each 10 cm dish, add 6.0 ml of complete medium with serum and antibiotics freshly 30~60 min before transfection.

Table 1. A Guideline for Seeding Adherent Cells Prior to Transfection in Different Culture Formats.

Culture Dish	Surface Area (cm ²)	Number of Cells to Seed
T75 Flask	75	3.0 - 6.0 × 10 ⁶
100 mm dish	58	2.2 - 4.4 × 10 ⁶
60 mm dish	21	0.9 - 1.8 × 10 ⁶
35 mm dish	9.6	3.5 - 7.0 × 10 ⁵
6-well plate	9.6	4.0 - 8.0 × 10 ⁵
12-well plate	3.5	1.5 - 3.0 × 10 ⁵
24-well plate	1.9	0.8 - 1.6 × 10 ⁵
48-well plate	1.0	4.0 - 8.0 × 10 ⁴

- For each dish, dilute total 12 µg of DNA (6.0 µg lenti-vector plasmid plus 6.0 µg lentivirus packaging mix) into 500 µL of serum-free DMEM with High Glucose. Vortex to mix.

- For each dish, dilute 40 µl of PeneFect™ reagent into 500 µl of serum-free DMEM with High Glucose. Vortex gently to mix.

Note: Never use Opti-MEM to dilute DNA and PeneFect™ reagent because it will disrupt transfection complex.

- Add the diluted PeneFect™ Reagent immediately to the diluted DNA solution all at once. (**Important:** do not mix the solutions in the reverse order!)

-Vortex-mix the solution immediately followed by incubation of 10 min at room temperature to allow PeneFect™/DNA complexes to form.

Note: Never keep the DNA/PeneFect™ complex longer than 20 min.

- Add the 1000 µl PolyJet™/DNA complex drop-wise onto the medium in each dish and homogenize the mixture by gently swirling the plate.

- Change medium 24 hrs after transfection followed by harvesting lentivirus from supernatant 48 hrs and 72 hrs post transfection.

Storage: PeneFect™ Transfection Reagent is stable for up to 12 months at 4°C.